

readme.md for @push.rocks/smartvpn

A high-performance VPN solution with a **TypeScript control plane** and a **Rust data plane daemon**. Enterprise-ready client authentication, triple transport support (WebSocket + QUIC + WireGuard), and a typed hub API for managing clients from code.

- ☐ **Noise IK** mutual authentication — per-client X25519 keypairs, server-side registry
- ☐ **Triple transport**: WebSocket (Cloudflare-friendly), raw **QUIC** (datagrams), and **WireGuard** (standard protocol)
- ☐ **ACL engine** — deny-overrides-allow IP filtering, aligned with SmartProxy conventions
- ☐ **PROXY protocol v2** — real client IPs behind reverse proxies (HAProxy, SmartProxy, Cloudflare Spectrum)
- ☐ **Per-transport metrics**: active clients and total connections broken down by websocket, QUIC, and WireGuard
- ☐ **Hub API**: one `createClient()` call generates keys, assigns IP, returns both SmartVPN + WireGuard configs
- ☐ **Real-time telemetry**: RTT, jitter, loss ratio, link health — all via typed APIs
- ☐ **Unified forwarding pipeline**: all transports share the same engine — TUN (kernel), userspace NAT (no root), or testing mode
- ☐ **Destination routing policy**: force-target, block, or allow traffic per destination with nftables integration
- ✗ **Handshake-driven WireGuard state**: peers appear as "connected" only after a successful WireGuard handshake, and auto-disconnect on idle timeout

Issue Reporting and Security


For reporting bugs, issues, or security vulnerabilities, please visit community.foss.global/. This is the central community hub for all issue reporting. Developers who sign and comply with our contribution agreement and go through identification can also get a code.foss.global/ account to submit Pull Requests directly.

Install ☐☐

```
pnpm install @push.rocks/smartvpn
# or
npm install @push.rocks/smartvpn
```

The package ships with pre-compiled Rust binaries for **linux/amd64** and **linux/arm64**. No Rust toolchain required at runtime.

Architecture



Split-plane design — TypeScript handles orchestration, config, and DX; Rust handles every hot-path byte with zero-copy async I/O (tokio, mimalloc).

IPC Transport Modes

The bridge between TypeScript and Rust supports two transport modes:

Mode	Use Case	How It Works
stdio	Development, testing	Spawns the Rust daemon as a child process, communicates over stdin/stdout
socket	Production	Connects to an already-running daemon via Unix domain socket, with optional auto-reconnect

```
// Development: spawn the daemon
const server = new VpnServer({ transport: { transport: 'stdio' } });

// Production: connect to running daemon
const server = new VpnServer({
  transport: {
    transport: 'socket',
```

```
    socketPath: '/var/run/smartvpn.sock',
    autoReconnect: true,
    reconnectBaseDelayMs: 100,
    reconnectMaxDelayMs: 5000,
    maxReconnectAttempts: 10,
  },
});
```

Quick Start

1. Start a VPN Server (Hub)

```
import { VpnServer } from '@push.rocks/smartvpn';

const server = new VpnServer({ transport: { transport: 'stdio' } });
await server.start({
  listenAddr: '0.0.0.0:443',
  privateKey: '<server-noise-private-key-base64>',
  publicKey: '<server-noise-public-key-base64>',
  subnet: '10.8.0.0/24',
  transportMode: 'all',          // WebSocket + QUIC + WireGuard simultaneously (default)
  forwardingMode: 'tun',        // 'tun' (kernel), 'socket' (userspace NAT), or 'testing'
  wgPrivateKey: '<server-wg-private-key-base64>', // required for WireGuard transport
  enableNat: true,
  dns: ['1.1.1.1', '8.8.8.8'],
});
```

2. Create a Client (One Call = Everything)

```
const bundle = await server.createClient({
  clientId: 'alice-laptop',
  serverDefinedClientTags: ['engineering'], // trusted tags for access control
  security: {
    destinationAllowList: ['10.0.0.0/8'], // can only reach internal network
    destinationBlockList: ['10.0.0.99'], // except this host
  }
});
```

```
    rateLimit: { bytesPerSec: 10_000_000, burstBytes: 20_000_000 },
  },
});

// bundle.smartvpnConfig → typed IVpnClientConfig, ready to use
// bundle.wireguardConfig → standard WireGuard .conf string
// bundle.secrets → { noisePrivateKey, wgPrivateKey } — shown ONCE
```

3. Connect a Client

```
import { VpnClient } from '@push.rocks/smartvpn';

const client = new VpnClient({ transport: { transport: 'stdio' } });
await client.start();

const { assignedIp } = await client.connect(bundle.smartvpnConfig);
console.log(`Connected! VPN IP: ${assignedIp}`);
```

Features □

□□ Enterprise Authentication (Noise IK)

Every client authenticates with a **Noise IK handshake** (`Noise_IK_25519_ChaChaPoly_BLAKE2s`). The server verifies the client's static public key against its registry — unauthorized clients are rejected before any data flows.

- Per-client X25519 keypair generated server-side
- Client registry with enable/disable, expiry, tags
- Key rotation with `rotateClientKey()` — generates new keys, returns fresh config bundle, disconnects old session

□□ Triple Transport

Transport	Protocol	Best For
WebSocket	TLS over TCP	Firewall-friendly, Cloudflare compatible

Transport	Protocol	Best For
QUIC	UDP (via quinn)	Low latency, datagram support for IP packets
WireGuard	UDP (via boringtun)	Standard WG clients (iOS, Android, wg-quick)

The server runs **all three simultaneously** by default with `transportMode: 'all'`. All transports share the same unified forwarding pipeline (`ForwardingEngine`), IP pool, client registry, and stats — so WireGuard peers get the same userspace NAT, rate limiting, and monitoring as WS/QUIC clients. Clients auto-negotiate with `transport: 'auto'` (tries QUIC first, falls back to WS).

☐☐ Per-Transport Metrics

Server statistics include per-transport breakdowns so you can see exactly how many clients use each protocol:

```
const stats = await server.getStatistics();

// Aggregate
console.log(stats.activeClients);      // total connected clients
console.log(stats.totalConnections);   // total connections since start

// Per-transport active clients
console.log(stats.activeClientsWebsocket); // currently connected via WS
console.log(stats.activeClientsQuic);     // currently connected via QUIC
console.log(stats.activeClientsWireguard); // currently connected via WireGuard

// Per-transport total connections
console.log(stats.totalConnectionsWebsocket);
console.log(stats.totalConnectionsQuic);
console.log(stats.totalConnectionsWireguard);
```

WireGuard connection state is handshake-driven — registered WireGuard peers do NOT appear as "connected" until their first successful WireGuard handshake completes. They automatically disconnect after 180 seconds of inactivity or when boringtun reports `ConnectionExpired`. This matches how WebSocket/QUIC clients behave: they appear on connection and disappear on disconnect.

☐☐ ACL Engine (SmartProxy-Aligned)

Security policies per client, using the same `ipAllowList` / `ipBlockList` naming convention as `@push.rocks/smartproxy`:

```
security: {
  ipAllowList: ['192.168.1.0/24'],          // source IPs allowed to connect
  ipBlockList: ['192.168.1.100'],          // deny overrides allow
  destinationAllowList: ['10.0.0.0/8'],    // VPN destinations permitted
  destinationBlockList: ['10.0.0.99'],     // deny overrides allow
  maxConnections: 5,
  rateLimit: { bytesPerSec: 1_000_000, burstBytes: 2_000_000 },
}
```

Supports exact IPs, CIDR, wildcards (`192.168.1.*`), and ranges (`1.1.1.1-1.1.1.100`).

☐ PROXY Protocol v2

When the VPN server sits behind a reverse proxy, enable PROXY protocol v2 to receive the **real client IP** instead of the proxy's address. This makes `ipAllowList` / `ipBlockList` ACLs work correctly through load balancers.

```
await server.start({
  // ... other config ...
  proxyProtocol: true,                // parse PP v2 headers on WS connections
  connectionIpBlockList: ['198.51.100.0/24'], // server-wide block list (pre-handshake)
});
```

Two-phase ACL with real IPs:

Phase	When	What Happens
Pre-handshake	After TCP accept	Server-level <code>connectionIpBlockList</code> rejects known-bad IPs — zero crypto cost
Post-handshake	After Noise IK identifies client	Per-client <code>ipAllowList</code> / <code>ipBlockList</code> checked against real source IP

- Parses the PP v2 binary header from raw TCP before WebSocket upgrade
- 5-second timeout protects against stalling attacks
- LOCAL command (proxy health checks) handled gracefully
- IPv4 and IPv6 addresses supported
- `remoteAddr` field on `IVpnClientInfo` exposes the real client IP for monitoring
- **Security:** must be `false` (default) when accepting direct connections — only enable behind a trusted proxy

☐☐ Destination Routing Policy

Control where decrypted VPN client traffic goes — force it to a specific target, block it, or allow it through. Evaluated per-packet before per-client ACLs.

```
await server.start({
  // ...
  forwardingMode: 'socket', // userspace NAT mode
  destinationPolicy: {
    default: 'forceTarget', // redirect all traffic to a target
    target: '127.0.0.1', // target IP for 'forceTarget' mode
    allowList: ['10.0.0.0/8'], // these destinations pass through directly
    blockList: ['10.0.0.99'], // always blocked (deny overrides allow)
  },
});
```

Policy modes:

Mode	Behavior
'forceTarget'	Rewrites destination IP to <code>target</code> — funnels all traffic through a single endpoint
'block'	Drops all traffic not explicitly in <code>allowList</code>
'allow'	Passes all traffic through (default, backward compatible)

In **TUN mode**, destination policies are enforced via **nftables** rules (using `@push.rocks/smarnftables`). A 60-second health check automatically re-applies rules if they're removed externally.

In **socket mode**, the policy is evaluated in the userspace NAT engine before per-client ACLs.

☐☐ Socket Forward Proxy Protocol

When using `forwardingMode: 'socket'` (userspace NAT), you can prepend **PROXY protocol v2 headers** on outbound TCP connections. This conveys the VPN client's tunnel IP as the source address to downstream services (e.g., SmartProxy):

```
await server.start({
  // ...
  forwardingMode: 'socket',
  socketForwardProxyProtocol: true, // downstream sees VPN client IP, not 127.0.0.1
});
```

```
});
```

☐☐ Packet Forwarding Modes

SmartVPN supports three forwarding modes, configurable per-server and per-client:

Mode	Flag	Description	Root Required
TUN	'tun'	Kernel TUN device — real packet forwarding with system routing	<input type="checkbox"/> Yes
Userspace NAT	'socket'	Userspace TCP/UDP proxy via <code>connect(2)</code> — no TUN, no root needed	<input type="checkbox"/> No
Testing	'testing'	Monitoring only — packets are counted but not forwarded	<input type="checkbox"/> No

```
// Server with userspace NAT (no root required)
await server.start({
  // ...
  forwardingMode: 'socket',
  enableNat: true,
});

// Client with TUN device
const { assignedIp } = await client.connect({
  // ...
  forwardingMode: 'tun',
});
```

The userspace NAT mode extracts destination IP/port from IP packets, opens a real socket to the destination, and relays data — supporting both TCP streams and UDP datagrams without requiring `CAP_NET_ADMIN` or root privileges.

☐☐ Telemetry & QoS

- **Connection quality:** Smoothed RTT, jitter, min/max RTT, loss ratio, link health (`healthy` / `degraded` / `critical`)
- **Adaptive keepalives:** Interval adjusts based on link health (60s → 30s → 10s)
- **Per-client rate limiting:** Token bucket with configurable bytes/sec and burst
- **Dead-peer detection:** 180s inactivity timeout (all transports)

- **MTU management:** Automatic overhead calculation (IP+TCP+WS+Noise = 79 bytes)
- **Per-transport stats:** Active client and total connection counts broken down by websocket, QUIC, and WireGuard

☐☐ Client Tags (Trusted vs Informational)

SmartVPN separates server-managed tags from client-reported tags:

Field	Set By	Trust Level	Use For
<code>serverDefinedClientTags</code>	Server admin (via <code>createClient</code> / <code>updateClient</code>)	☐ Trusted	Access control, routing, billing
<code>clientDefinedClientTags</code>	Client (reported after connection)	△ Informational	Diagnostics, client self-identification
<code>tags</code>	<i>(deprecated)</i>	—	Legacy alias for <code>serverDefinedClientTags</code>

```
// Server-side: trusted tags
await server.createClient({
  clientId: 'alice-laptop',
  serverDefinedClientTags: ['engineering', 'office-berlin'],
});

// Client-side: informational tags (reported to server)
await client.connect({
  // ...
  clientDefinedClientTags: ['macOS', 'v2.1.0'],
});
```

☐☐ Hub Client Management

The server acts as a **hub** — one API to manage all clients:

```
// Create (generates keys, assigns IP, returns config bundle)
const bundle = await server.createClient({ clientId: 'bob-phone' });

// Read
const entry = await server.getClient('bob-phone');
const all = await server.listRegisteredClients();
```

```
// Update (ACLs, tags, description, rate limits...)
await server.updateClient('bob-phone', {
  security: { destinationAllowList: ['0.0.0.0/0'] },
  serverDefinedClientTags: ['mobile', 'field-ops'],
});

// Enable / Disable
await server.disableClient('bob-phone'); // disconnects + blocks reconnection
await server.enableClient('bob-phone');

// Key rotation
const newBundle = await server.rotateClientKey('bob-phone');

// Export config (without secrets)
const wgConf = await server.exportClientConfig('bob-phone', 'wireguard');

// Remove
await server.removeClient('bob-phone');
```

☐☐ WireGuard Config Generation

Generate standard `.conf` files for any WireGuard client:

```
import { WgConfigGenerator } from '@push.rocks/smartvpn';

const conf = WgConfigGenerator.generateClientConfig({
  privateKey: '<client-wg-private-key>',
  address: '10.8.0.2/24',
  dns: ['1.1.1.1'],
  peer: {
    publicKey: '<server-wg-public-key>',
    endpoint: 'vpn.example.com:51820',
    allowedIps: ['0.0.0.0/0'],
    persistentKeepalive: 25,
  },
});

// → standard WireGuard .conf compatible with wg-quick, iOS, Android
```

Server configs too:

```
const serverConf = WgConfigGenerator.generateServerConfig({
  privateKey: '<server-wg-private-key>',
  address: '10.8.0.1/24',
  listenPort: 51820,
  enableNat: true,
  natInterface: 'eth0',
  peers: [
    { publicKey: '<client-wg-public-key>', allowedIps: ['10.8.0.2/32'] },
  ],
});
```

☐☐ System Service Installation

Generate systemd (Linux) or launchd (macOS) service units:

```
import { VpnInstaller } from '@push.rocks/smartvpn';

const unit = VpnInstaller.generateServiceUnit({
  binaryPath: '/usr/local/bin/smartvpn_daemon',
  socketPath: '/var/run/smartvpn.sock',
  mode: 'server',
});

// unit.platform    → 'linux' | 'macos'
// unit.content     → systemd unit file or launchd plist
// unit.installPath → /etc/systemd/system/smartvpn-server.service
```

You can also call `generateSystemdUnit()` or `generateLaunchdPlist()` directly for platform-specific options like custom descriptions.

☐☐ Events

Both `VpnServer` and `VpnClient` extend `EventEmitter` and emit typed events:

```
server.on('client-connected', (info: IVpnClientInfo) => {
  console.log(`${info.registeredClientId} connected from ${info.remoteAddr} via
  ${info.transportType}`);
});
```

```

server.on('client-disconnected', ({ clientId, reason }) => {
  console.log(`${clientId} disconnected: ${reason}`);
});

client.on('status', (status: IVpnStatus) => {
  console.log(`State: ${status.state}, IP: ${status.assignedIp}`);
});

// Both server and client emit:
server.on('exit', ({ code, signal }) => { /* daemon process exited */ });
server.on('reconnected', () => { /* socket transport reconnected */ });

```

Event	Emitted By	Payload
status	Both	IVpnStatus — connection state changes
error	Both	{ message, code? }
client-connected	Server	IVpnClientInfo — full client info including transport type
client-disconnected	Server	{ clientId, reason? }
exit	Both	{ code, signal } — daemon process exited
reconnected	Both	void — socket transport reconnected

API Reference

Classes

Class	Description
VpnServer	Manages the Rust daemon in server mode. Hub methods for client CRUD, telemetry, rate limits, WireGuard peer management.
VpnClient	Manages the Rust daemon in client mode. Connect, disconnect, status, telemetry.
VpnBridge<T>	Low-level typed IPC bridge (stdio or Unix socket). Handles spawn, connect, reconnect, and typed command dispatch.

Class	Description
VpnConfig	Static config validation and JSON file I/O. Validates keys, addresses, CIDRs, MTU, etc.
VpnInstaller	Generates systemd/launchd service files for daemon deployment.
WgConfigGenerator	Generates standard WireGuard <code>.conf</code> files (client and server).

Key Interfaces

Interface	Purpose
IVpnServerConfig	Server configuration (listen addr, keys, subnet, transport mode, forwarding mode, clients, proxy protocol, destination policy)
IVpnClientConfig	Client configuration (server URL, keys, transport, forwarding mode, WG options, client-defined tags)
IClientEntry	Server-side client definition (ID, keys, security, priority, server/client tags, expiry)
IClientSecurity	Per-client ACLs and rate limits (SmartProxy-aligned naming)
IClientRateLimit	Rate limiting config (bytesPerSec, burstBytes)
IClientConfigBundle	Full config bundle returned by <code>createClient()</code> — includes SmartVPN config, WireGuard <code>.conf</code> , and secrets
IVpnClientInfo	Connected client info (IP, stats, authenticated key, remote addr, transport type)
IVpnServerStatistics	Server stats with per-transport breakdowns (activeClientsWebsocket/Quic/Wireguard, totalConnections*)
IVpnConnectionQuality	RTT, jitter, loss ratio, link health
IVpnMtuInfo	TUN MTU, effective MTU, overhead bytes, oversized packet stats
IVpnKeypair	Base64-encoded public/private key pair
IDestinationPolicy	Destination routing policy (forceTarget / block / allow with allow/block lists)
IVpnEventMap	Typed event map for server and client EventEmitter

Server IPC Commands

Command	Description
<code>start</code> / <code>stop</code>	Start/stop the VPN listener
<code>createClient</code>	Generate keys, assign IP, return config bundle
<code>removeClient</code> / <code>getClient</code> / <code>listRegisteredClients</code>	Client registry CRUD
<code>updateClient</code> / <code>enableClient</code> / <code>disableClient</code>	Modify client state
<code>rotateClientKey</code>	Fresh keypairs + new config bundle
<code>exportClientConfig</code>	Re-export as SmartVPN config or WireGuard <code>.conf</code>
<code>listClients</code> / <code>disconnectClient</code>	Manage live connections
<code>setClientRateLimit</code> / <code>removeClientRateLimit</code>	Runtime rate limit adjustments
<code>getStatus</code> / <code>getStatistics</code> / <code>getClientTelemetry</code>	Monitoring (stats include per-transport breakdowns)
<code>generateKeypair</code> / <code>generateWgKeypair</code> / <code>generateClientKeypair</code>	Key generation
<code>addWgPeer</code> / <code>removeWgPeer</code> / <code>listWgPeers</code>	WireGuard peer management

Client IPC Commands

Command	Description
<code>connect</code> / <code>disconnect</code>	Manage the tunnel
<code>getStatus</code> / <code>getStatistics</code>	Connection state and traffic stats
<code>getConnectionQuality</code>	RTT, jitter, loss, link health
<code>getMtuInfo</code>	MTU and overhead details

Transport Modes

Server Configuration

```
// All transports simultaneously (default) – WS + QUIC + WireGuard
{ transportMode: 'all', listenAddr: '0.0.0.0:443', wgPrivateKey: '...', wgListenPort: 51820 }

// WS + QUIC only
{ transportMode: 'both', listenAddr: '0.0.0.0:443', quicListenAddr: '0.0.0.0:4433' }

// WebSocket only
```

```

{ transportMode: 'websocket', listenAddr: '0.0.0.0:443' }

// QUIC only
{ transportMode: 'quic', listenAddr: '0.0.0.0:443' }

// WireGuard only
{ transportMode: 'wireguard', wgPrivateKey: '...', wgListenPort: 51820, wgPeers: [...] }

```

All transport modes share the same `forwardingMode` — WireGuard peers can use `'socket'` (userspace NAT) just like WS/QUIC clients.

Client Configuration

```

// Auto (tries QUIC first, falls back to WS)
{ transport: 'auto', serverUrl: 'wss://vpn.example.com' }

// Explicit QUIC with certificate pinning
{ transport: 'quic', serverUrl: '1.2.3.4:4433', serverCertHash: '<sha256-base64>' }

// WireGuard
{ transport: 'wireguard', wgPrivateKey: '...', wgEndpoint: 'vpn.example.com:51820', ... }

```

Cryptography

Layer	Algorithm	Purpose
Handshake	Noise IK (X25519 + ChaChaPoly + BLAKE2s)	Mutual authentication + key exchange
Transport	Noise transport state (ChaChaPoly)	All post-handshake data encryption
Additional	XChaCha20-Poly1305	Extended nonce space for data-at-rest
WireGuard	X25519 + ChaCha20-Poly1305 (via boringtun)	Standard WireGuard crypto

Binary Protocol

All frames use `[type:1B][length:4B][payload:NB]` with a 64KB max payload:

Type	Hex	Direction	Description
HandshakeInit	0x01	Client → Server	Noise IK first message
HandshakeResp	0x02	Server → Client	Noise IK response
IpPacket	0x10	Bidirectional	Encrypted tunnel data
Keepalive	0x20	Client → Server	App-level keepalive (not WS ping)
KeepaliveAck	0x21	Server → Client	Keepalive response with RTT payload
Disconnect	0x3F	Bidirectional	Graceful disconnect

Development

```
# Install dependencies
pnpm install

# Build (TypeScript + Rust cross-compile)
pnpm build

# Run all tests
pnpm test

# Run Rust tests directly
cd rust && cargo test

# Run a specific TS test
tstest test/test.flowcontrol.node.ts --verbose
```

Project Structure

```
smartvpn/
├─ ts/                # TypeScript control plane
│  └─ index.ts        # All exports
│  └─ smartvpn.interfaces.ts # Interfaces, types, IPC command maps
│  └─ smartvpn.plugins.ts # Dependency imports
│  └─ smartvpn.paths.ts # Binary path resolution
```

```

|   └─ smartvpn.classes.vpnserver.ts
|   └─ smartvpn.classes.vpnclient.ts
|   └─ smartvpn.classes.vpnbridge.ts
|   └─ smartvpn.classes.vpnconfig.ts
|   └─ smartvpn.classes.vpninstaller.ts
|   └─ smartvpn.classes.wgconfig.ts
└─ rust/                                # Rust data plane daemon
|   └─ src/
|       └─ main.rs                      # CLI entry point
|       └─ server.rs                   # VPN server + hub methods
|       └─ client.rs                   # VPN client
|       └─ crypto.rs                   # Noise IK + XChaCha20
|       └─ client_registry.rs          # Client database
|       └─ acl.rs                      # ACL engine
|       └─ proxy_protocol.rs           # PROXY protocol v2 parser
|       └─ management.rs               # JSON-lines IPC
|       └─ transport.rs                # WebSocket transport
|       └─ transport_trait.rs          # Transport abstraction (Sink/Stream)
|       └─ quic_transport.rs           # QUIC transport
|       └─ wireguard.rs                # WireGuard (boringtun)
|       └─ codec.rs                    # Binary frame protocol
|       └─ keepalive.rs                # Adaptive keepalives
|       └─ ratelimit.rs                # Token bucket
|       └─ userspace_nat.rs            # Userspace TCP/UDP NAT proxy
|       └─ tunnel.rs                   # TUN device management
|       └─ network.rs                  # IP pool + networking
|       └─ telemetry.rs                # RTT/jitter/loss tracking
|       └─ qos.rs                      # Priority queues + smart dropping
|       └─ mtu.rs                      # MTU + ICMP too-big
|       └─ reconnect.rs                # Exponential backoff + session tokens
└─ test/                                # Test files
└─ dist_ts/                             # Compiled TypeScript
└─ dist_rust/                           # Cross-compiled binaries (linux amd64 + arm64)

```

License and Legal Information

This repository contains open-source code licensed under the MIT License. A copy of the license can be found in the [LICENSE](#) file.

Please note: The MIT License does not grant permission to use the trade names, trademarks, service marks, or product names of the project, except as required for reasonable and customary use in describing the origin of the work and reproducing the content of the NOTICE file.

Trademarks

This project is owned and maintained by Task Venture Capital GmbH. The names and logos associated with Task Venture Capital GmbH and any related products or services are trademarks of Task Venture Capital GmbH or third parties, and are not included within the scope of the MIT license granted herein.

Use of these trademarks must comply with Task Venture Capital GmbH's Trademark Guidelines or the guidelines of the respective third-party owners, and any usage must be approved in writing. Third-party trademarks used herein are the property of their respective owners and used only in a descriptive manner, e.g. for an implementation of an API or similar.

Company Information

Task Venture Capital GmbH
Registered at District Court Bremen HRB 35230 HB, Germany

For any legal inquiries or further information, please contact us via email at hello@task.vc.

By using this repository, you acknowledge that you have read this section, agree to comply with its terms, and understand that the licensing of the code does not imply endorsement by Task Venture Capital GmbH of any derivative works.

Revision #7

Created 2026-03-28 11:13:46 UTC by foss.global Team

Updated 2026-03-31 14:22:35 UTC by foss.global Team